



Exam 6

Digit Span Test

Participant ID #:

Acrostic:

Technician ID:

Date: / /
Month Day Year

DIGIT SPAN TEST - - FORWARD

- After saying the instructions administer the digit spans in order.
- Do not repeat a span once read.
- Administer both spans of the same length regardless of how the participant performs.
- Say the digits at a rate of 1 digit about every 1 sec.
- Use a monotonic voice; without inflections at the end
- Do not 'chunk' spans (e.g., 34-729) when you read them
- Discontinue after failure on both trials of any item (e.g., 5a and 5b)

Examiner: "我要說一些數字，請仔細聽，並當我說完後跟著我說。例如，如果我說7—1—9，你應該說什麼？"

- If the participant responds correctly (7-1-9), say: "正確" and proceed to Item 1.
- If the participant fails the example, say: "不對，你要說 7—1—9，我說7—1—9，所以你要從前往後說7—1—9。現在試一試 從前往後說 3—4—8。"
- Whether the participant succeeds or fails with the second example (3-4-8), proceed to Item 1. Give no help on this second example or any of the items that follow.

Scoring: Each span is scored '1' (Pass) or '0' (Fail). Only discontinue test when participant has failed both trials of the same span length (e.g., 5a and 5b).

Item	Digit Span	Pass	Fail
1. a.	1 - 7	<input type="radio"/> 1	<input type="radio"/> 0
b.	6 - 3	<input type="radio"/> 1	<input type="radio"/> 0
2. a.	5 - 8 - 2	<input type="radio"/> 1	<input type="radio"/> 0
b.	6 - 9 - 4	<input type="radio"/> 1	<input type="radio"/> 0
3. a.	6 - 4 - 3 - 9	<input type="radio"/> 1	<input type="radio"/> 0
b.	7 - 2 - 8 - 6	<input type="radio"/> 1	<input type="radio"/> 0
4. a.	4 - 2 - 7 - 3 - 1	<input type="radio"/> 1	<input type="radio"/> 0
b.	7 - 5 - 8 - 3 - 6	<input type="radio"/> 1	<input type="radio"/> 0
5. a.	6 - 1 - 9 - 4 - 7 - 3	<input type="radio"/> 1	<input type="radio"/> 0
b.	3 - 9 - 2 - 4 - 8 - 7	<input type="radio"/> 1	<input type="radio"/> 0
6. a.	5 - 9 - 1 - 7 - 4 - 2 - 8	<input type="radio"/> 1	<input type="radio"/> 0
b.	4 - 1 - 7 - 9 - 3 - 8 - 6	<input type="radio"/> 1	<input type="radio"/> 0
7. a.	5 - 8 - 1 - 9 - 2 - 6 - 4 - 7	<input type="radio"/> 1	<input type="radio"/> 0
b.	3 - 8 - 2 - 9 - 5 - 1 - 7 - 4	<input type="radio"/> 1	<input type="radio"/> 0
8. a.	2 - 7 - 5 - 8 - 6 - 2 - 5 - 8 - 4	<input type="radio"/> 1	<input type="radio"/> 0
b.	7 - 1 - 3 - 9 - 4 - 2 - 5 - 6 - 8	<input type="radio"/> 1	<input type="radio"/> 0



Exam 6

Digit Span Test

DIGIT SPAN TEST - - BACKWARD

- Administer the digit spans in order.
- Do not repeat a span once read.
- Administer both spans of the same length regardless of how the participant performs.
- Say the digits at a rate of 1 digit about every 1 sec.
- Use a monotonic voice; without inflections at the end
- Do not 'chunk' spans (e.g., 34-729) when you read them
- Discontinue after failure on both trials of any item (e.g., 5a and 5b)

Examiner: "現在我要說一些數字，但這次當我停下來時我要你從後往前說。例如，如果我說7—1—9，你應該說什麼？"

- If the participant responds correctly (9-1-7), say: "正確" and proceed to Item 1.
- If the participant fails the example, say: "不對，你要說9—1—7，我說7—1—9，所以你要從後往前說9—1—7。現在試一試這些數字，記住，你要從後往前說3—4—8。"
- Whether the participant succeeds or fails with the second example (3-4-8), proceed to Item 1. Give no help on this second example or any of the items that follow.

Scoring: Each span is scored '1' (Pass) or '0' (Fail). Only discontinue test when participant has failed both trials of the same span length (e.g., 5a and 5b).

Item	Digit Span	Pass	Fail
1. a.	2 - 4	<input type="radio"/> 1	<input type="radio"/> 0
b.	5 - 7	<input type="radio"/> 1	<input type="radio"/> 0
2. a.	6 - 2 - 9	<input type="radio"/> 1	<input type="radio"/> 0
b.	4 - 1 - 5	<input type="radio"/> 1	<input type="radio"/> 0
3. a.	3 - 2 - 7 - 9	<input type="radio"/> 1	<input type="radio"/> 0
b.	4 - 9 - 6 - 8	<input type="radio"/> 1	<input type="radio"/> 0
4. a.	1 - 5 - 2 - 8 - 6	<input type="radio"/> 1	<input type="radio"/> 0
b.	6 - 1 - 8 - 4 - 3	<input type="radio"/> 1	<input type="radio"/> 0
5. a.	5 - 3 - 9 - 4 - 1 - 8	<input type="radio"/> 1	<input type="radio"/> 0
b.	7 - 2 - 4 - 8 - 5 - 6	<input type="radio"/> 1	<input type="radio"/> 0
6. a.	8 - 1 - 2 - 9 - 3 - 6 - 5	<input type="radio"/> 1	<input type="radio"/> 0
b.	4 - 7 - 3 - 9 - 1 - 2 - 8	<input type="radio"/> 1	<input type="radio"/> 0
7. a.	9 - 4 - 3 - 7 - 6 - 2 - 5 - 8	<input type="radio"/> 1	<input type="radio"/> 0
b.	7 - 2 - 8 - 1 - 9 - 6 - 5 - 3	<input type="radio"/> 1	<input type="radio"/> 0